

QueueMetrics 20.11 WebRTC SoftPhone - FreePBX PJSIP setup



QueueMetrics 20.11 WebRTC SoftPhone - FreePBX PJSIP setup

In this tutorial we will go through the necessary steps to setup the latest version of the QueueMetrics Softphone. With the latest version we strongly recommend you switch to PJSIP extensions, following the recommendations of various PBX manufacturers.

QueueMetrics

QueueMetrics is a highly scalable monitoring software that lets you track agent productivity, payrolls, measure targets, conversion rates, ACD, IVR, Music on hold, generate outbound campaign statistics and monitor realtime processes with customizable wallboards.

You can measure all contact centre activities with more than 200 different metrics and manage realtime processes with extensions and calls control, live alarms, whisper mode, spy and barge mode.

Prerequisites

A QueueMetrics Live instance or a QueueMetrics on-premise installation (20.11.8 at the time of writing), with SSL configured.

If you are not sure how to setup SSL for your QueueMetrics on-premise, please follow our manual.

A valid SSL certificate should also be added to FreePBX's Certificate Manager. <u>A Let's Encrypt certificate</u> is a valid solution if you don't know where to start.

To add a certificate to FreePBX, please follow the relevant documentation.

FreePBX Setup

TLS/WSS Setup

First of all, we need to enable WSS transport for PJSIP extensions.

To do this, navigate to Settings => Asterisk SIP Settings => General SIP Settings

General SIP Settings	SIP Settings [chan_pjsip]	SIP Legacy Settings [chan_sip]
These settings apply to bot	h 'SIP Settings [chan_pjsip]' and	'Slp Legacy Settings [chan_slp]'.
-Security Settings		
Allow Anonymous Inbound	d SIP Calls 😧	Yes No
Allow SIP Guests 😮		Yes No
Default TLS Port Assignme	nt 🛛	Chan SIP PJSip
NAT Settings		
External Address 🕢		
		Detect Network Settings
Local Networks 😮		/
		Add Local Network Field

-DTD Settings

And make sure your NAT settings are correct (if any). You can use the Detect Network Settings button to automatically configure these settings.

Once this is done, navigate to the pjsip tab:

SIP Settings [chan_pjsip]

Here we need to specify that we want our PJSIP extensions to use TLS and set the transport protocol to WSS. We also need to specify the certificate we want to use to guarantee the connection.

First, let's select the certificate mentioned in the prerequisites as the TLS transport certificate.

TLS/SSL/SRTP Settings => Certificate Manager

Then, down below, enable WSS transport.

WSS - 0.0.0.0 - All = Yes

Once you have done this, you can submit and save your changes.

Extension Setup

Let's create a new PJSIP extension by navigating to

Applications => Extensions => Add Extension => Add New SIP [chan_pisip] Extension

tension:	100				
General	Voicemail	Find Me/Follow Me	Advanced	Pin Sets	Other
- Edit Exte	ension				
This devic	ce uses PJSIP tec	hnology listening on Port 5	6060 (UDP)		
Display Na	ame 0				100
Outbound	CID 📀				
Emergency	y CID 👴				
Secret 🛛					arrana
- Languag	ţe				
Language	Code 😡				Default
- User Ma	nager Settin	gs			
Linked to Us	ser 100				
Select Use	r Directory: 😣				PBX Internal Directory
Link to a D	Different Defaul	t User: 🥹			100 (Linked)
Username	0				Use Custom Username
Password	For New User 📢	•			19424/14/06/00/01/01/06/70/4/70/7
Groups 😏					All Users ×

We set the Display Name and Secret for our new extension, then navigate to the Advanced tab.

Here, we need to set the following options:

Value
Yes
Yes
Yes
DTLS-SRTP
0.0.0-wss
Yes
Yes
The same certificate mentioned in the prerequisites
Fingerprint
Act/Pass
0

	Qualify Frequency 😧	60	
	Transport 🛛	0.0.0-wss	
	Enable AVPF 📀	No Yes	
	Enable ICE Support 📀	No Yes	
	Enable rtcp Mux 😧	No Yes	
	Call Crowner O		
N	lediaEncryption 🕢	DTLS-SRTP (not recommended)	
c	ossion Timors O	Vac	

DTLS	
Enable DTLS 📀	No Yes
Auto Generate Certificate 🧿	No Yes
Use Certificate 🕜	default
DTLS Verify 👔	Fingerprint
DTLS Setup 🕖	Act/Pass
DTLS Rekey Interval 📀	0

Once we have done this, the extension is ready. We can then save and apply our changes.

QueueMetrics Setup

To Create and agent, linked to the Asterisk Extension we created earlier (100 in our case), go to Agents \rightarrow Create New.

+	~		Configuration
Realtime Comprehensive view of Live calls	Wallboards Customizable wallboards for live d Agents and Queues General Into	Reports Historical reports All Reports Quark Agents Report Quark reports	Users Queues Agent Coups Locations Call fratures Call Fratures Call Fratures Call Fratures Call Fratures Fratures Pause Codes IVR Selections
News QueueMetrics Latest News • This week only: Introducing QwueMetrics 20:11 • QueueMetrics 20:11 is out • Time to update QwueMetrics • A status update from Loway	Synchronizer QueueMetrics Automatic Setup		DIDDNIS Lines Agent Stalls Known Numbers QA Forms CBTS QA Performance Tracker Edit Scheduled Jobs Edit Report Exports System Administration

We call the agent Agent/100 and fill in the Agent Description field as we please. We then fill the following fields:

WebPhone Username with the extension username we previously set (in this case 100).

WebPhone Password with the extension secret we previously set (in this case mysecretpassword).

WebPhone Realm with the address of our FreePBX machine. (in this case myfreepbx.com).

5		
Current terminal:		
Instant messenger address:	TES	тт
WebPhone Username:	100	
WebPhone Password:	mysecretpassword	
WebPhone Realm:	myfreepbx.com	
WebPhone SIP Uri:		
Auto Answer	No	v

We click on Save then go back to the Homepage.

Now we need to create a User for Agent/100, so we go to Users \rightarrow Create New.

We set the Login field to 100, the Password to 100 and we set the Class field to AGENTS.

User Detail	
User Id:	
Login:	agent/100
Password:	***
Confirm Password:	***
Real name:	WebRTC 100
Enabled:	Yes 👻
E-mail:	
Masterkey:	No
Class:	AGENTS

We click on Save and we go back to the homepage.

The last thing we need to do is to set one parameter in the Explore System Parameters page. Scroll down to the end of the page until you see the following parameter: Web Socket URL for the connection.

We need to set this, using the correct IP address for our FreePBX machine. Then we Save our file.

Agent Page Softphone Settings	
Maximum interval in seconds between WebSocket reconnection attemps. Default value is 30.	30
Minimum interval in seconds between WebSocket reconnection attemps. Default value is 2.	2
Web Socket LIDL for the compaction	
Web Jocket Orce for the connection.	wss://myfreepbx.com:8089/ws

Now we're good to go! We log out of our QueueMetrics Administrator Account and we login as Agent/100.

From the Widget Menu we select Soft Phone and here is our WebRTC client.

Soft Phone				0		
ବୃତ୍ତ Agent :100			¢			
1 Dial	1	2 ABC	3 DEF			
	4 GHI	5 IKL	6 MNO			
	7 PQRS	8 TUV	9 WXYZ			
	*	0	#			
	•	٩.	Ų			

Now you can make and receive calls, as long as you give the webpage permission to use your microphone and headphones/speakers, when prompted.

Troubleshooting

The Softphone is not registering

If the softphone is unable to register with the PBX, it will look like this:

1 Dial	1	2	3
	4	5	6
	7	8	9
	*	0	#
	9	•	Ţ

Usually this can happen due to various reasons:

1) The username or password for the extension are not correct

2) The PBX address is incorrect

3) The extension is a PJSIP extension, but the websocket is currently listening for SIP connections.

1 and 2 are easy to fix, as we just need to check all our settings again and make sure they are correct.

Number 3 is a fairly common occurrence, that can be fixed by following these steps.

NOTE: To fix this issue you will need to restart the PBX, so make sure you do this during an appropriate maintenance window.

Navigate to

Settings => Asterisk Sip Settings => Chan SIP Settings => Advanced General Settings => Other SIP Settings.

and add the following value in the left field>

websocket_enabled			
-------------------	--	--	--

and this other value in the right field

false	
Call Events 🕑	Yes No
Other SIP Settings 😧	websocket_enabled = false
	Add Field

Save, apply and then we will need to restart the PBX.

NOTE: This will interrupt the PBX operations so make sure you are outside of production time

astersik -rx 'core restart now'

Now the PBX should have PJSIP listening on the WSS WebSocket. Refresh the agent page and check if the phone is now able to register correctly.

The Softphone is registering but calls hang up immediately

This can happen if the browser does not have access to the Microphone or the Speakers/Headphones. Make sure you have assigned the permissions correctly, and that you do not have another tab in the same browser that is currently using the Microphone.

Another reason for calls hanging up immediately, could be that the extension settings regarding AVPF, encryption and the like, specified in this tutorial, have not been set correctly.

The Softphone can make calls, but no audio is heard

This is usually due to NAT settings. If your PBX has NAT enabled, we need to set at least one ICE Server(STUN) to make sure that the audio streams are exchanged correctly. To do this we need to first choose a STUN server, for example:

stun.l.google.com:19302

and add it to both the Softphone configuration in QueueMetrics, and FreePBXs SIP configuration.

To set it in QueueMetrics, go to Explore System Parameters and set the List of ICE Servers to use. parameter under Agent Page Softphone Settings (if you are using the SoftPhone from the Wallboard page you will need to edit the same setting under Wallboard Softphone Settings.

once you find the correct option, set it to:

stun:stun.l.google.com:19302

Save and go to FreePBX's GUI. Here we need to navigate to Settings =h Asterisk Sip Settings => General Sip Settings => Stun Server Address

and add the server like this:

stun.l.google.com:19302

NOTE: In QueueMetrics you need to prefix the server with "stun:".

Save and apply your changes in the PBX, and reload the agent page. You should now hear audio on your calls.

QueueMetrics References

QueueMetrics software is available on premise or as a cloud hosted service for FreePBX, Yeastar S PBX, Grandstream, Issabel, FusionPBX and many other Asterisk distros.

For more technical information please refer to the User Manual.

Visit <u>www.queuemetrics.com</u> for a free 30 days full featured trial.

Attend our <u>Free Webinars</u> for a live demonstration of QueueMetrics.